



PATCHWORK APRON TUTORIAL

Step-by-Step Guide to Make Your Own Apron



MATERIALS

- 5 cotton fabrics (quilting weight)
- Matching thread or contrast thread
- 2 large buttons (2.5–3 cm)
- Sewing machine
- Iron and ironing board
- Scissors / Rotary cutter
- Pins / Clips
- Measuring tape


FABRIC SUGGESTION



FINISHED SIZE

Width: 68 cm
Length: 80 cm
(excluding straps)

PATTERN (with 1 cm seam allowance included)



CUTTING GUIDE

	Red Floral Upper Left	Cut 1 – 40 x 34 cm
	Yellow Upper Right	Cut 1 – 40 x 34 cm
	Green Lower Left	Cut 1 – 40 x 34 cm
	Cream Floral Lower Right (Top part)	Cut 1 – 26 x 34 cm
	Teal Lower Right (Bottom part)	Cut 1 – 14 x 34 cm

POCKETS

Cream Floral Pocket
Cut 1 – 20 x 24 cm



Teal Pocket
Cut 1 – 20 x 24 cm



STEP-BY-STEP ASSEMBLY

1



PIECE THE FRONT

Sew the 5 fabric pieces together to form the apron front.

2



MAKE THE POCKETS

Fold the top edge of each pocket 1 cm to the wrong side and press. Stitch around the sides and bottom.

3



ATTACH THE POCKETS

Place pockets on the front panel as shown and topstitch around the sides and bottom.

4



PREPARE THE BACK

Place the front and back panel (wrong sides together). Pin and sew around the sides and bottom.

5



MAKE THE STRAPS

Fold each strap in half lengthwise (right sides together). Sew along the long edge, turn right side out and press.

6



ATTACH STRAPS & BUTTONS

Attach the straps to the top corners. Overlap the ends and sew buttons on the front. Adjust for desired length.

FINISHING

- Press the apron well.
- Topstitch around the top edge for a clean finish.
- Your patchwork apron is ready to use!



FRONT VIEW



BACK VIEW



MAIN SEWING METHODS



Straight Stitch
Used for all seams.



Topstitch
Stitch on the right side for a decorative finish.



Pressing
Press seams open or to one side for a neat look.



Seam Allowance
All seams include 1 cm unless noted.

TIPS

- Use 100% cotton fabric for best results.
- Pre-wash and iron fabrics before cutting.
- Adjust strap length for a perfect fit.
- This apron also makes a wonderful handmade gift!



CARE INSTRUCTIONS



Machine wash cold



Do not bleach




Tumble dry low



Iron medium if needed

MADE WITH LOVE






Enjoy your handmade apron every day!



PATCHWORK APRON SEWING PATTERN

Finished Size: One Size Fits Most
(Adjust the strap length as needed)

--- SEAM ALLOWANCE 1/2" (1.25 cm)
Cut along the solid line
Sew along the dashed line



INSTRUCTIONS:

- Cut all pieces as indicated.
- Add interfacing to pocket top facing (optional).
- Sew pocket facing to the pocket. Turn and topstitch.
- Attach pockets to the apron body as desired.
- Attach neck strap through button holes and tie waist ties at the back.
- Press all seams well.



All measurements include
1/2" (1.25 cm) seam allowance.

<https://creative.craftsforlove.com/> - **SEE THE BEST PATTERNS**

Patchwork Apron Tutorial: Step-by-Step Guide to Make Your Own Apron

This colorful patchwork apron is made from five coordinating cotton fabrics, two practical front pockets, adjustable shoulder straps, and decorative buttons. The finished apron measures approximately 68 cm wide by 80 cm long—about $26\frac{3}{4} \times 31\frac{1}{2}$ inches—not including the straps.

The instructions below follow the measurements, construction order, and sewing methods shown in the tutorial chart. Metric measurements are the primary measurements, with approximate inch conversions included for sewists in the United States.

Materials and Sewing Supplies

Gather all materials before cutting the fabric:

- Five coordinating cotton fabrics in quilting weight
- Matching or contrasting all-purpose sewing thread
- Two large buttons measuring approximately 2.5–3 cm, or 1–1 $\frac{1}{4}$ inches
- Sewing machine
- Iron and ironing board
- Fabric scissors or rotary cutter
- Cutting mat and quilting ruler
- Straight pins or sewing clips
- Measuring tape
- Fabric marking pen or tailor's chalk
- Hand-sewing needle for securing the buttons
- Paper for drafting the full-size apron pattern

Choose fabrics that look balanced when placed together. The illustrated apron uses:

- Red floral cotton
- Mustard-yellow cotton
- Olive-green cotton
- Cream floral cotton
- Teal cotton

Prewash and dry all cotton fabrics before cutting. This prevents unexpected shrinking after the apron is finished. Press every fabric carefully so the pieces are flat and easy to measure.

Use a 1 cm seam allowance, approximately $\frac{3}{8}$ inch, throughout the project unless another measurement is specifically noted.

Finished Apron Size

The completed apron body should measure approximately:

- Width: 68 cm or about $26\frac{3}{4}$ inches
- Length: 80 cm or about $31\frac{1}{2}$ inches
- Top edge: 24 cm or about $9\frac{1}{2}$ inches
- Strap length: 60 cm or about $23\frac{5}{8}$ inches
- Finished strap width: approximately 3 cm or about $1\frac{1}{4}$ inches, depending on the folding method

The apron has a full lower section with curved sides that narrow toward the upper chest area. The two straps extend upward from the top corners.

The pattern includes a 1 cm seam allowance.

Drafting the Main Apron Pattern

Tape several sheets of paper together or use a large piece of pattern paper.

Draw a vertical center line measuring 80 cm, or approximately 31½ inches.

At the lower end of the center line, draw a horizontal line measuring 68 cm, or approximately 26¾ inches. Center this line so that 34 cm extends to each side of the vertical center line.

At the upper end, draw a horizontal line measuring 24 cm, or approximately 9½ inches. Center this line so that 12 cm extends to each side of the center line.

From each end of the 24 cm top line, draw a short line downward. Begin shaping the apron sides by drawing a gentle outward curve from the upper section toward the wider body.

Continue each curve until it blends into the straight lower side of the apron. The curved section should create comfortable arm openings without making the upper chest area too narrow.

Draw straight side lines from the bottom of each curve to the lower corners.

Check that both sides are symmetrical. The easiest method is to draw only half of the pattern, fold the paper along the center line, and cut through both paper layers.

Label the pattern:

- **Patchwork Apron Front**
- **Cut 1 assembled patchwork panel**
- **Apron Back**
- **Cut 1 from teal fabric**
- **1 cm seam allowance included**
- **Cut on grain**

The chart shows the front and back as matching body shapes. Once the patchwork front is assembled, it will be trimmed using this full-size pattern.

Cutting the Patchwork Front Pieces

Cut the five sections indicated in the chart:

- Red floral upper-left section: cut 1 at 40 × 34 cm
- Yellow upper-right section: cut 1 at 40 × 34 cm
- Green lower-left section: cut 1 at 40 × 34 cm
- Cream floral lower-right upper section: cut 1 at 26 × 34 cm
- Teal lower-right bottom section: cut 1 at 14 × 34 cm

Approximate inch conversions are:

- 40 × 34 cm: about $15\frac{3}{4} \times 13\frac{3}{8}$ inches
- 26 × 34 cm: about $10\frac{1}{4} \times 13\frac{3}{8}$ inches
- 14 × 34 cm: about $5\frac{1}{2} \times 13\frac{3}{8}$ inches

These sections create an oversized rectangular patchwork panel. After sewing them together, the panel is centered beneath the apron pattern and trimmed to the final apron shape.

Before sewing, arrange the pieces on a flat surface:

- Red floral at the upper left
- Yellow at the upper right
- Green at the lower left
- Cream floral at the lower-right upper area
- Teal at the lower-right bottom area

Check the direction of any floral or directional prints before joining the pieces.

Cutting the Apron Back

Place the main apron pattern on the teal cotton fabric.

Align the center line and grainline with the fabric grain. Pin or weight the pattern securely.

Cut one complete apron back.

Transfer any useful pattern marks, including:

- **Center top**
- **Center bottom**
- **Strap placement**
- **Arm curve beginning points**

Keep the back piece flat while constructing the front.

Cutting the Straps

Cut two strap rectangles measuring:

- **8 × 60 cm each**
- **Approximately 3¹/₈ × 23⁵/₈ inches each**

The finished straps will be narrower after folding and stitching.

The chart shows one red floral strap and one teal strap. You may follow this arrangement or cut both straps from the same fabric.

For longer or shorter straps, adjust the length before sewing. The 60 cm length works well for many adults, but it is helpful to hold a fabric strip against the body before completing the straps.

Cutting the Pockets

The finished pocket pattern measures approximately:

- **Width: 18 cm or about 7¹/₈ inches**

- Length: 20 cm or about 7⁷/₈ inches

The lower corners taper toward a short pointed edge.

For construction, cut each pocket at approximately:

- 20 × 24 cm
- About 7⁷/₈ × 9¹/₂ inches

The additional fabric allows for the top hem, turned side edges, bottom edge, and seam allowance.

Cut:

- One pocket from cream floral fabric
- One pocket from teal fabric

To form the pointed bottom, mark the center of the lower edge. Measure upward along both side edges to establish the beginning of the angled corners. Draw diagonal lines from those side marks toward a short centered lower edge.

Make sure the two pocket shapes are the same size before pressing.

Step 1: Piece the Patchwork Apron Front

Begin by joining the cream floral and teal pieces that form the lower-right section.

Place the cream floral piece and teal piece right sides together, matching the 34 cm edges that will be joined.

Pin or clip the layers.

Sew with a 1 cm seam allowance using a straight stitch.

Press the seam first while it is closed. Then press the seam allowance toward the darker teal fabric or press it open to reduce bulk.

Next, place the red floral and yellow upper pieces right sides together.

Match the long vertical edges and pin them carefully.

Sew with a 1 cm seam allowance.

Press the seam neatly.

Place the green lower-left piece beside the joined cream-and-teal lower-right section.

With right sides together, align the vertical edges.

Sew the seam and press it flat.

You should now have two larger rows:

- **An upper row made from red floral and yellow fabric**
- **A lower row made from green, cream floral, and teal fabric**

Place the upper and lower rows right sides together.

Match the center vertical seam of the upper row with the appropriate seam or placement point in the lower row. Pin from the center outward so the fabric does not shift.

Sew across the horizontal seam using a 1 cm seam allowance.

Press the seam carefully. You now have one complete patchwork panel.

Topstitching close to the patchwork seams is optional. It can help the seam allowances remain flat and add a decorative quilted appearance.

Step 2: Trim the Front to the Apron Shape

Press the assembled patchwork panel thoroughly.

Place it right side up on a large cutting surface.

Position the paper apron pattern over the patchwork panel. Arrange it so that the fabric colors appear balanced inside the finished shape.

The red floral and yellow fabrics should remain in the upper section. The green, cream floral, and teal fabrics should remain in the lower portion.

Pin the paper pattern securely or hold it with pattern weights.

Cut around the full apron pattern.

Mark the center top and all strap placement points.

Compare the patchwork front with the teal back. They should have the same shape and dimensions.

Make small corrections before continuing, but avoid cutting deeply into the arm curves.

Step 3: Make the Pockets

Place each pocket wrong side up on the ironing board.

Fold the top edge toward the wrong side by 1 cm, approximately $\frac{3}{8}$ inch, and press.

Fold the top edge over again by approximately 2 cm, or about $\frac{3}{4}$ inch, to create a clean double-fold hem.

Press and pin the top hem.

Stitch across the folded top edge close to the lower fold. You may add a second row of topstitching near the upper edge for a decorative finish.

Fold the side edges and pointed lower edges toward the wrong side by approximately 1 cm.

Use a pocket template cut from cardboard to help maintain an accurate shape. Place the template on the wrong side, fold the seam allowances around it, and press.

Clip or carefully trim excess fabric at bulky lower corners if necessary. Do not cut too close to the fold.

Remove the cardboard template and press each pocket again.

The top edge should already be finished, while the sides and lower edges remain folded under.

Step 4: Position the Pockets

Lay the patchwork front right side up.

Position the cream floral pocket over the green lower-left section.

Position the teal pocket over the cream floral lower-right section.

The pockets should appear balanced and should be placed at a comfortable hand height. Keep them far enough from the apron's side seams so they will not be caught when the front and back are joined.

Use a ruler to check that both pocket openings are at approximately the same height.

Pin or clip each pocket in place.

For extra security, baste the pockets before permanent stitching.

Topstitch around the side and lower edges of each pocket. Leave the upper edge completely open.

Begin at one upper corner, sew down the side, follow the angled lower edge, continue across the short bottom, sew up

the opposite angles and side, and stop at the other upper corner.

Backstitch securely at both ends.

For stronger pockets, sew a small triangle or narrow rectangle at each upper corner. These areas receive the most stress during use.

Press the attached pockets.

Step 5: Prepare the Apron Back

Inspect the teal back piece and make sure the edges match the patchwork front.

Staystitch around the curved arm openings if the fabric seems likely to stretch. Sew approximately 6 mm, or $\frac{1}{4}$ inch, from the raw edge.

Staystitching is a regular straight stitch sewn just inside the seam allowance. It stabilizes curved and bias-cut edges.

Mark the center top of the back.

Lay the front over the back with wrong sides facing temporarily to confirm that the shapes are identical.

Trim only tiny uneven areas if needed.

Step 6: Join the Apron Front and Back

Place the patchwork front and teal back right sides together.

Match:

- Top edges
- Arm curves
- Side edges

- Lower corners
- Bottom edge

Pin or clip around the entire apron.

Leave an opening of approximately 12–15 cm, or about 5–6 inches, along one lower side or the bottom edge. This opening will be used to turn the apron right side out.

Sew around the apron with a 1 cm seam allowance. Do not sew across the turning opening.

Use a regular stitch length of approximately 2.5 mm.

Sew slowly around the arm curves. Stop with the needle down whenever you need to adjust the fabric.

Backstitch at both sides of the turning opening.

Step 7: Grade, Clip, and Turn the Apron

Before turning, reduce bulk in the seam allowances.

Trim the seam allowance slightly at the corners without cutting through the stitching.

Clip small V-shaped notches from the outer curves and make straight clips into the inner curves. Stop 2–3 mm before the seam.

Grading the seam allowances can also create a smoother finish. Trim one layer slightly narrower than the other so the edges do not stack directly on top of each other.

Turn the apron right side out through the opening.

Use a blunt point turner, chopstick, or capped pen to gently shape the corners. Do not use sharp scissors because they may puncture the fabric.

Roll the seams between your fingers so the joining seam sits directly on the edge.

Press the apron thoroughly.

At the turning opening, fold the raw edges inward so they align with the sewn seam. Press and pin the opening closed.

Step 8: Topstitch the Apron

Topstitch around the entire outer edge approximately 3–6 mm, or $\frac{1}{8}$ – $\frac{1}{4}$ inch, from the edge.

The topstitching closes the turning opening and gives the apron a clean, professional finish.

Use matching thread for a subtle result or contrasting thread for a decorative outline.

Keep the stitching distance consistent around:

- Top edge
- Arm curves
- Side edges
- Lower edge

Lengthen the stitch slightly to approximately 3 mm for attractive topstitching.

Pivot carefully at corners with the needle lowered into the fabric.

Press the apron after topstitching.

Step 9: Make the Shoulder Straps

Place one strap rectangle wrong side up.

Fold it in half lengthwise, bringing the two long edges together. Press to mark the center crease.

Open the strip.

Fold each long raw edge inward until it meets the center crease.

Press both folds.

Fold the strip in half again along the original center crease. All long raw edges should now be enclosed.

The folded strap will measure approximately 2 cm wide if folded exactly into quarters. A slightly wider finished strap can be created by using a narrower fold at each edge. Follow the visual proportions shown in the chart.

Tuck each short end inward by approximately 1 cm for a clean finish.

Pin or clip along the strap.

Topstitch close to the open long edge, sewing through all folded layers.

For a more polished result, topstitch along the opposite long edge as well.

Repeat for the second strap.

Press both finished straps.

Step 10: Attach the Straps

Position one strap at each upper corner of the apron.

The illustrated design places the red floral strap on the viewer's right and the teal strap on the viewer's left.

Overlap the lower end of each strap onto the apron by approximately 3–4 cm, or about 1¼–1½ inches.

Make sure the straps are straight and extend upward without twisting.

Pin the straps temporarily.

Try the apron on or place it against the intended wearer.

Check:

- Apron height
- Strap spacing
- Strap length
- Chest coverage
- Comfort around the shoulders

Adjust the overlap until the apron sits at the desired height.

Stitch each strap securely to the upper apron corner. Sew a rectangle around the overlapped area, then sew an X inside the rectangle for reinforcement.

The tutorial also shows one large button at each upper corner. Position the button over the reinforced strap attachment.

Hand-sew each button securely using doubled thread.

Pass the needle through the button several times, knot the thread firmly on the back, and hide the thread tails between the apron layers when possible.

The buttons are decorative unless you choose to create functioning buttonholes in the straps.

Step 11: Final Pressing and Finishing

Inspect all seams and remove loose threads.

Press the apron from the front and back.

Pay special attention to:

- Patchwork seams
- Pocket edges
- Arm curves
- Top edge
- Bottom edge
- Straps

For a clean finish, add another line of topstitching around the upper edge if desired.

Check that both pockets are fully attached and that the openings remain unobstructed.

Gently pull on each strap to confirm that it is securely sewn.

Make sure the buttons are firmly attached and cannot be pulled loose during normal use.

The patchwork apron is now complete and ready to wear.

Main Sewing Methods Used

Straight Stitch

A straight stitch is used for all construction seams.

Recommended settings:

- **Stitch length: 2.5 mm for construction**
- **Stitch length: 3 mm for visible topstitching**
- **Universal needle: size 80/12 for quilting cotton**
- **1 cm seam allowance unless otherwise noted**

Backstitch at the beginning and end of seams that will not be crossed by another seam.

Topstitching

Topstitching is visible stitching sewn on the right side of the project.

It is used to:

- **Secure pocket edges**
- **Close the turning opening**
- **Finish the apron perimeter**
- **Keep the straps flat**
- **Add a decorative detail**

Sew slowly and keep the edge aligned with a mark on the presser foot.

Pressing

Press each seam after it is sewn.

Do not move the iron back and forth aggressively because this can stretch the fabric. Lower and lift the iron while applying gentle pressure.

Press patchwork seams toward the darker fabric when possible. Press the apron's outer seam carefully after turning.

Seam Allowance

All main seams include a 1 cm seam allowance, approximately $\frac{3}{8}$ inch.

Consistent seam allowances help the patchwork sections fit together and keep the finished apron symmetrical.

Use a seam guide on the sewing machine if necessary.

Helpful Tips

Use 100% quilting cotton for the best combination of structure, comfort, and easy sewing.

Prewash fabrics before cutting, especially when combining strong colors such as red, teal, and yellow. A color-catching laundry sheet can help reduce dye transfer.

Use a fresh rotary-cutter blade for accurate patchwork pieces.

Label every cut piece with removable notes before sewing.

Check the print direction before joining floral sections.

Press every seam before adding another piece. Accurate pressing is essential for neat patchwork.

When pinning the upper and lower patchwork rows, begin at the center and work outward.

Use a longer strap when making the apron for a tall wearer.

Before permanently attaching the straps, try the apron on and confirm the fit.

For additional stability, lightweight woven interfacing may be added to the strap pieces before folding.

A walking foot can help when topstitching through the front, back, and seam allowances.

Reinforce the pocket corners because these points receive frequent pulling.

This handmade apron also makes a thoughtful gift for a baker, gardener, crafter, quilter, or home cook.

Care Instructions

Wash the apron in a washing machine on a cold, gentle cycle.

Use mild detergent.

Do not use chlorine bleach, especially on the red, yellow, and teal fabrics.

Tumble dry on low or air-dry the apron to reduce shrinking and preserve the colors.

Remove it promptly from the dryer to minimize wrinkles.

Press with an iron on a medium cotton setting when necessary.

Check the care instructions for the decorative buttons before placing the apron in a dryer. Remove delicate buttons before washing if they are not washable.

Store the apron hanging from its straps or folded neatly in a drawer.

Your handmade patchwork apron is now ready for cooking, crafting, sewing, gardening, or gifting.

<https://creative.craftsforlove.com/> - **SEE THE BEST PATTERNS**